

Z80ASM
Z80 Relocating Macro Assembler

USER'S GUIDE

Copyright (c) 1984 by
SLR Systems
1622 N. Main Street
Butler, PA 16001
(412) 282-0864

COPYRIGHT NOTICE

This software product is distributed for the use of the original purchaser only, and no license is granted herein to copy, duplicate, sell or otherwise distribute to any other person, firm, or entity. Furthur, this software product and all forms of the program are copyrighted by SLR Systems, and all rights are reserved.

TRADEMARKS

Wherever referred to throughout this manual, CP/M and Z80 are registered trademarks of Digital Research and Zilog, Inc., respectively.

INTRODUCTION

Z80ASM is a powerful relocating macro assembler for Z80-based CP/M systems. It takes assembly language source statements from a disk file, converts them into their binary equivalent, and stores the output in either a core-image, Intel hex format, or relocatable object file. The mnemonics recognized are those of Zilog/Mostek. The optional listing output may be sent to a disk file, the console and/or the printer, in any combination. Output files may also be generated containing cross-reference information on each symbol used.

FEATURES

- 1) One pass operation (optional second pass)
- 2) Powerful nested macros, conditionals, and include files
- 3) Relocatable format allows extended math on externals and relocatables
- 4) Up to 15 different data, program, and common areas
- 5) Zilog/Mostek mnemonics
- 6) Throughput of over 6000 Lines/Minute (8"SS/SD, 2Mhz)
- 7) Optional alphabetized symbol table
- 8) Optional alphabetized cross-reference
- 9) Directly generates a .COM, .HEX, or .REL file
- 10) Labels Significant to 16 characters
- 11) Supports time and date in listing
- 12) User Configurable
- 13) Supports ZCPR3 and CP/M+ error reporting

TABLE OF CONTENTS

	Section - Page
Introduction	i-2
Features	i-2
Table of Contents	i-3
Running the Assembler	1-1
Command Line Options	1-3
Source Line Format	2-1
Expressions	2-4
Relocatability	2-7
Pseudo Operations	3-0
Program Counter Maintenance	3-1
Data Definition and Generation	4-1
Conditional Assembly	5-1
Macro Facility	6-1
Listing Controls	7-1
Miscellaneous	8-1
APPENDIX A - Error Message Summary	A-1
APPENDIX B - Zilog Z80 Instr. Set	B-1
APPENDIX C - Intel HEX file format	C-1
APPENDIX D - CONFIG Utility	D-1
APPENDIX E - ASCII Table	E-1
APPENDIX F - Warranty	F-1

RUNNING THE ASSEMBLER

To run the assembler, type

```
A > Z80ASM [COMMAND][,COMMAND]
```

where the brackets are not really typed, and what is enclosed in them is optional. If no COMMAND's are given on the initial command line, **Z80ASM** will prompt for a command line with a percent (%) sign. **Z80ASM** allows as many commands to be given as will fit on a 128 character line. Commands are separated by a comma. Note that input from the prompt is via the Read Console Buffer system call, so that commands may be passed through a SUBMIT file. However, there is a better way...

COMMANDS are defined as follows:

```
<Filename>[.<Drive >][/<Option>]
```

where <Filename> is the source file with the (default) extension Z80.

. is a separator used only when <Drive> is present.

<Drive> is used to modify the default drive selection. The default condition selects the CP/M default drive for source file, enables binary output to the default drive, and enables the disk listing driver to the default drive. <Drive> is from one to three letters (@-P, where @ is the default drive) defined as follows:

first letter: drive on which <Filename>.Z80 is located

second letter: selects drive to receive output file - to disable binary file generation, use a Z in this location. If this letter is missing, output will go to the default drive.

third letter: selects the drive or device on which to place the listing output. If selected, the cross-reference and symbol table also go to this device. To send the output to a disk file, use a valid drive letter in this location. To output just to the console, use an X; Y selects output to the list device. If no listing-type output is desired, use a Z in this spot. If this letter is missing, output will go to the default drive.

/ is optional, but must be used when <Option> is used.

<Option> is one or more of the following letters, in any order:

- A : absolute mode. Output file is COM.
- C : enables output to the console.
- D : don't do LOWER to UPPER case conversion.
- E : execute LOWER to UPPER case conversion.
- F : selects full listing (2 passes through source).
- H : generate HEX file as output.
- I : special indirect command file.
- K : kill all console I/O and detach.
- L : list output partial (1 pass through source).
- M : generate Microsoft REL file as output.
- N : new OPTION byte.
- P : enables output to the list device.
- Q : quit, abort.
- R : generate standard REL file as output.
- S : generate alphabetized symbol table.
- T : input time and date string.
- U : declares undefined symbols as external.
- X : generates cross-reference.
- Y : disable cross-reference.
- 6 : selects M-Rel output, 6 significant.
- 7 : selects M-Rel output, 7 significant.

For example, assuming standard default conditions:

```
A>Z80ASM EXAMPLE/F,DUMP.ABZ/SXRP
```

tells **Z80ASM** to assemble A:EXAMPLE.Z80, create A:EXAMPLE.COM as the binary output, and create A:EXAMPLE.LST as the second pass full listing output. Next assemble A:DUMP.Z80, creating an S-REL file on drive B, and generating a symbol table and cross-reference on the printer.

Efficiency Hints

1. Use one-pass mode wherever possible. The only time two pass mode is necessary is generating a cross-reference, or a listing with forward references resolved.
2. If generating a one-module program, generate the COM or HEX output directly from the assembler.
3. For multiple module work, use an indirect file. For most assemblies, a major percentage of the assembly time is merely loading in the assembler. **Z80ASM** will assemble all the files in an indirect file without reloading the assembler.
4. If you CONFIGure in a 2nd pass listing or cross-reference, you will ALWAYS get 2-pass mode unless you use the proper switches to disable it (/N).

Let's talk in more detail about the command line options.

COMMAND LINE OPTIONS

Command line options are used to modify the default operating characteristics of **Z80ASM**. This is the default mode as supplied by SLR Systems (the default mode may be modified by the user by running the CONFIG utility):

Generate a core-image .COM file on one pass through the source, converting lower-case items to upper-case, generate no listing output, no symbol table output, and no cross-reference output.

So, if you wanted to assemble the file DUMP.Z80 (included on your distribution diskette) to create the file DUMP.COM, both on drive B:, with no other output, you would type

```
A>Z80ASM DUMP.BB
```

Note that the Z was not needed in the listing drive spot since no listing-type output was requested. If the files were on drive A,

```
A>Z80ASM DUMP
```

would produce the desired result.

There are many other available options though, and this section describes them in a little more detail.

A

The A option selects absolute mode operation and a default output file type of COM. This is the standard default mode, so it will not need to be used unless the default mode has been modified.

C

The C option enables the console output driver. This has no effect in itself, but if any listing, symbol table or cross-reference outputs are selected, these items will be output to the console device (Error messages are always enabled to the console, unless /K is used).

D

The D option disables LOWER to UPPER case conversion. This is used when it is desired to have upper and lower case characters treated differently, such as when assembling output from a C compiler. Note that when this is in effect, reserved words (mnemonics, registers, and pseudo-ops) may be in any case or mixture. .LIST may be redefined as a macro, and .LIST will still be recognized as a pseudo-op.

E

The E option enables LOWER to UPPER case conversion. This is the standard default mode. Note that the conversion only affects characters not inside quoted strings, and that lower case characters are still lower case in a list file.

F

The F option selects FULL listing mode. This option forces Z80ASM into 2-pass mode, generating a listing output on the second pass to any and all enabled devices. Note that by default the disk driver is enabled.

H

The H option selects a binary output type compatible with the Intel HEX format.

I

The I option is a special case option used for indirect command file input. If this option is used, it can be the only option specified. The /I option causes **Z80ASM** to read the file <FILENAME>.SUB on the default drive (or the selected source drive) for its command lines. This is similar to using SUBMIT and XSUB except that 1) it is much faster, 2) it can be used from within a SUBMIT file, 3) it can be used without XSUB and SUBMIT leaving more RAM available for the assembly, and 4) it can be used while A: is not the default drive.

K

The K option kills all console I/O, including error messages. Also, under multitasking systems, a 'detach console' is issued slipping **Z80ASM** into the background.

L

The L option selects one-pass listing mode. This listing is similar to the F-mode full listing except that forward references list as undefined in the generated code columns. Note that by default the output will go to the default disk drive.

M

The M option forces relocatable mode. The binary output file has the default extension REL, and the format generated is compatible with the Microsoft relocatable format.

N

The N option is used to start over with new options. For instance, if you have M-REL format with symbol table and XREF selected from CONFIG, N will delete those options and put you back to the standard default mode.

P

The P option enables the PRINTER or CP/M list device output driver. Any listing, symbol table, or cross-reference output selected will be sent to the CP/M list device. Error messages will also be sent to the printer, even if no other listing output has been selected.

Q

The Q option is used to abort interactive command line acceptance. It is identical in function to a control-C, but it may also be used at other than the beginning of the line, from SUBMIT files, and from INDIRECT command files, all places where ^C is illegal.

R

The R option is used to select relocatable operation. The output file type is REL, and the format generated is SLR Format.

S

The S option selects the generation of an alphabetized symbol table. The output goes to all enabled devices. The output contains symbol names, types, and values. The number of symbols per line depends on the selected page width.

T

The T option is used to specify a time and date string for use in generating listings. Any following characters (up to 16) up to the next comma or carriage return are used as the time and date string. This option must be used as the last slash option. The input string is used automatically for subsequent assemblies unless overridden by another T option, or **Z80ASM** is reloaded.

U

The U option (ignored in absolute mode) instructs **Z80ASM** to automatically declare any UNDEFINED labels as externals to be resolved by the linker.

X

The X option selects cross-reference generation. This option forces two-pass mode, and the output will go to all enabled devices.

Y

The Y option deletes the XREF option if it was already selected (like from CONFIG).

6

The 6 option performs an implied M option, and selects 6 significant character generation for globals and externals. This overrides the default selected by CONFIG.

7

The 7 option does the same as 6 except that **Z80ASM** will generate 7 significant characters for globals and externals.

ASSEMBLER RUNTIME CONTROL

There are several operations available at the console while **Z80ASM** is in operation. For instance, at any time, a ^C (Control-C) may be typed, causing **Z80ASM** to abort the assembly of the current file. This allows you to abort the assembly of a large file that had the wrong command line options, without rebooting.

Assembly operation may be temporarily halted with a ^S, and resumed with a ^Q.

The Console driver may be enabled and disabled (toggled) with a ^Z, and the list device driver may be toggled with a ^P. Note that these may be used whether or not their drivers were enabled in the command line. These are very useful for watching just some of the assembly where errors are occurring, or printing out just part of the assembly without inserting LIST and NLIST pseudo-ops in the source (if you are quick!).

A '?' causes **Z80ASM** to display the current filename and line number in the file so you can see exactly how things are progressing.

Any other character is merely echoed on the console and ignored.

SOURCE LINE FORMAT

Source input to the assembler comes from a disk. Each line of input must be less than 128 characters, and must be terminated by a CR-LF sequence. Input lines follow the following syntax:

```
[Line #] [Label[:]] [Operation] [Parameters] [Comment]
```

where anything inside brackets is optional.

Each line is processed one at a time. First, if lower to upper case conversion is enabled (as in the standard default case), any lower case characters not inside quotation marks are converted to upper case, so that upper and lower case characters are interchangeable for labels, opcodes, etc.

Line #

The line number is an optional field which contains a valid number. This item is optional and is ignored by the assembler.

Label

Labels or symbols are made up of characters from the following set:

```
%      $      ?      .      @      0-9      A-Z      a-z      _
```

The first character of a label must not be from 0-9.

Symbols may be any length, however only the first 16 characters are significant. This rule holds true throughout unless M-REL operation is selected, in which case sixteen characters are still significant internally, but only six or seven (see CONFIG) are passed to the linker for entry points and external references. S-REL format allows full 16 significant characters on all references.

The colon following a label is optional in most instances. Two exceptions are 1) when the label is a reserved word, and 2) when the label is defined as both a macro and a label. In both these cases, the colon is required to distinguish the label from the reserved word or macro reference.

The following are valid symbols used as labels:

```
Label          ??ERROR          @spec
Never_Again    $12345           .ABCDEFGHIJKL
```

This example shows the colon used only where it is required:

```

0100 CPIR      MACRO      XX      ;Changes CPIR to a JP
0200          JP        XX
0300          ENDM
0400
0500 Start
0600          CPIR      CPIR      ;Means Jump to Label CPIR
0700 CPIR:    ;Colon skips scanning the
0800          END          ;Macro and reserved word
0900          ;tables

```

Labels may start in any column.

Operation

This item can be one of the standard Zilog mnemonics for a Z80 instruction, one of the standard **Z80ASM** pseudo-ops, or a user-defined macro instruction. The macro table is searched first, allowing redefinition of any opcodes or pseudo-ops.

The standard Zilog mnemonics are defined well in other publications, so we will not discuss them in too much detail here, but several things should be pointed out.

For ease of use, **Z80ASM** will except long and short forms for the 8-bit operations. For instance, in Zilog mnemonics, to add 5 to the accumulator, you say

```
ADD A, 5
```

which makes sense. To add with carry the same thing, you say

```
ADC A, 5
```

which still makes sense. Subtract with carry is the same way, but Subtract without carry is different. It is used like this:

```
SUB 5
```

which is not very consistent. At times it can be hard to remember which form is needed.

Z80ASM alleviates this problem of inconsistency by accepting both forms for all 8-bit operations. For example,

```
ADD  A, 5      ;produces what you would expect
ADD  5          ;produces the same thing
ADC  A, 5      ;Yep
ADC  5          ;Same thing
SBC  A, 5      ;Again
SBC  5          ;Same thing
CP   0f0h      ;generates a 0FEH, 0F0H
CP   A,0f0h    ;so does this
```

are all acceptable statements to **Z80ASM**. Use whichever you wish. However, for portability, you may want to adhere to the strict syntax.

Another comment should be made about the operation field. If **Z80ASM** is configured not to require colons on labels not starting in column 1, there is an area of ambiguity if you type an operation incorrectly. For instance, if you wanted the instruction OTIR, but incorrectly entered it:

```
OUTIR          ;OUTPUT ENTIRE BLOCK
```

Z80ASM will not generate an error, will not generate the proper code for OTIR, but will happily define a label OUTIR at that location. The only way **Z80ASM** will catch an error like that is if you do it twice, which will generate a 'previously defined' symbol error. For this reason it is recommended that you select colon requirements.

Parameters

These may be the operands required by the given opcode or pseudo-op, or may be parameters to a macro instruction. Expressions and macros will be discussed later.

Comments

Comments must start with a semicolon ';'. Everything on the line after the semicolon is ignored by the assembler.

EXPRESSIONS

Operands often consist of expressions. Expressions are merely combinations of operators and operands. For example,

1 3+5 -Start HIGH 0FE23h

are all valid expressions. Expressions can often get much more complex than that. If there is more than one operator in an expression, the expression is evaluated in the order of the operator 'precedence'. This table lists all the available operators, their functions, and their precedences.

<u>Operator</u>	<u>Function</u>	<u>Precedence</u>
-	Unary Minus	1
+	Unary Plus	1
NOT or ~	Bitwise NOT	1
HIGH	Take HIGH Byte	1
LOW	Take LOW Byte	1
NUL	Special NUL	1
TYPE	Returns Type	1
*	Unsigned Multiply	2
/	Unsigned Divide	2
MOD	Unsigned Modulo	2
SHR or >>	Shift Right	2
SHL or <<	Shift Left	2
+	Add	3
	Subtract	3
EQ or =	Equal	4
NE or <>	Not Equal	4
LT or <	Less Than	4
LE or <=	Less Than or Equal	4
GT or >	Greater Than	4
GE or >=	Greater Than or Equal	4
AND or &	Bitwise AND	5
XOR	Bitwise XOR	6
OR or	Bitwise OR	6

Some operators have equivalent forms, i.e.,

XM & 3 is identical to XM AND 3

in all respects. Note that the spaces around the '&' are not necessary, but are recommended to lessen the chances of confusion in macro processing. Embedded spaces are allowed between any items in an expression.

Default operator precedence may of course be overridden by use of parentheses. Be careful not to use parentheses at both ends of an expression unless you mean 'contents of'. For instance,


```
LD      HL,(1+3)*(4+7)      ;is treated as LD  HL,(44)
                                ;not LD  HL,44 as you would expect.
```

Note also that the characters (, [, and { are equivalent, as are),], and }, and may be used interchangeably. However, (and) are recommended for transportability and future compatibility.

A special case of an expression is the null expression, valid only in index register instructions. For example

```
LD      D,(IX)      ;is identical to  LD  D,(IX+0)
```

and is perfectly legal.

TYPE

The TYPE operator needs some explanation. It is a unary operator that returns the type of its operand expression. The type is defined as follows:

If the expression contains a forward reference, or is complicated enough to be sent to the linker to be resolved at link time, TYPE returns a ZERO. If the expression contains an external symbol plus or minus a constant or relative item, TYPE returns an 80H. Otherwise, the expression is defined locally, and TYPE returns a 20H plus one of the following:

0	if absolute
1	if CSEG relative
2	if DSEG relative
3	if relative to a common block

This is used mainly in handling macro parameters.

NUMBERS

Numbers are by default radix 10. The default radix may be overridden by using one of the following forms:

nB	Binary
nO	Octal
nQ	Octal
nD	Decimal
nH	Hexadecimal
X'n'	Hexadecimal

where n is any number of digits valid for the given radix. Note that the nB and nD forms will not be recognized if the default radix has been changed to larger than 11 or 13 respectively since the trailing character would be a valid digit in the default radix. Also, the first digit in the nH-type must be from 0-9.

SPECIAL SYMBOLS

A \$ is recognized as a special symbol representing the load counter at the beginning of the current statement or substatement. For instance, to loop forever:

```
JR    $
```

is the same as

```
HERE:    JR    HERE
```

since \$ is the load counter at the beginning of the instruction.

STRINGS

Strings are sequences of characters delimited by either single or double quote pairs. For example,

```
'This is a string'
"This is also a string"
'This is not a legal string'
```

Strings may contain quotation marks, and are defined in several possible ways. A single quote may be contained in a string delimited by double quotes, and vice versa, by just using it:

```
'This is an "easy" example'
"It isn't nice to fool mother nature"
```

Of course, you can use a single quote in a single quote string by just using it twice, and the same holds for double quote strings.

```
"This is an ""easy"" example"
'It isn''t nice to fool mother nature'
```

RELOCATABILITY

Many applications require the generation of relocatable code. This section describes the legal operations available on relocatable items.

What is a relocatable item? It is any item that is not defined at assembly time, but will be defined at link time. These items may be program relative, data relative, common relative, external, or any mathematical combination of the above items with other relocatable items or absolute items.

A special relocatable type is a relative type. A relative type is a program, data, or common relative item. Certain combinations of relatives generate absolute results, mainly a relative item minus another relative of the same type. For instance, a program relative item minus a program relative item yields an absolute result. Any other combination of relatives yields a "relocatable" item.

Absolutes may be added to or subtracted from relatives, yielding another relative.

Certain pseudo-ops require absolute values, such as "if" statements. Expressions that yield relative or relocatable results are illegal there and also in DEFS, etc.

Certain pseudo-ops can accept relative parameters. These are EQU, DEFL, .PHASE, and ORG.

Most other places where expressions are involved, any relocatable expression is allowed.

Suppose you wanted to load HL with a number equal to the distance from a data segment location to a program segment item. With most relocatable assemblers, this cannot be done directly. It must be calculated at run time like this:

```
LD      HL,DATAITEM
LD      DE,PROGITEM
OR      A
SBC     HL,DE
```

Z80ASM allows you to do directly what you originally wanted:

```
LD      HL,DATAITEM-PROGITEM
```

Obviously that can't be resolved at assembly time, so the expression is passed in reverse polish form to **SLRNK** for resolution at link time.

Certain combinations are not allowed in standard Microsoft format output; **SLRNK** Appendix B lists the operations that are legal and those **SLR Systems** has added. All combinations are allowed for use between **Z80ASM** and **SLRNK**, but certain operators are "extensions".

For example, you can generate a byte as a result of one or more relocatables like this:

```
LD      E,DATAITEM*EXTERNAL1+EXTERNAL2
```

SLRNK will give an error message if the result is out of range for a byte quantity.

It might even be nice to have a library routine that turns on a green light by setting the correct bit of a memory location, with the bit # depending on the application. You could then say

```
SET     GREEN-1,(HL)      ;TURN ON GREEN LIGHT
```

where **GREEN** is an external. **SLR** Format and modified **M-REL** can both handle that case.

PSEUDO-OPERATIONS

Z80ASM makes many pseudo-ops available to the assembly language programmer. They will be described in this section.

The pseudo-ops available are divided into 6 categories for this discussion. The categories are

1. Program Counter Maintenance
2. Data Definition and Generation
3. Conditional Assembly
4. Macro Facility
5. Listing Control
6. Miscellaneous Pseudo-ops

Here comes the first category!

1. PROGRAM COUNTER MAINTENANCE

This category includes pseudo-ops that control the program counter and the loading address of the generated code.

ABS**ASEG**

Absolute Segment. In a relative-mode assembly, this opcode causes **Z80ASM** to generate code for execution at a particular address, in this case, the address after the last absolute byte generated. If this is the first ASEG, then the address is 100H. This is very similar to absolute MODE except that code generated still has access to other relocatable items, such as externals. The generated code still needs to be linked before execution. This pseudo-op takes no parameters. This pseudo-op is ignored in absolute mode.

ORG <EXP>

Origin Program Location. This pseudo-op is used to specify a loading address <EXP> for the code that follows. The logical program counter is also set to <EXP>. The expression must yield an absolute or relative result defined on pass 1. ORG forces the mode of the expression. For example, if the expression yields a data-relative result, ORG forces an implied DSEG first. If the expression is absolute mode, ORG forces an implied ABS pseudo-op first:

```
ORG            100H
```

will cause code to be generated starting at address 100H. This is the default condition in absolute mode.

If no parameter is given, ORG returns the PC back to the value just preceding the last ORG.

CSEG
PROG
REL

Select Code or Program Loading Counter. This pseudo-op selects the code segment loading address and logical program counter. This is the default address space in relative mode. The address selected is that of the last code segment address used, which starts at 0. This pseudo-op is used to return to the code segment after having switched to another address space. For example,

```

0000' 21 0000"          LD  HL,MESG      ;Load Pointer to Mes
0003' CD 0000#          CALL OUTPUT      ;Output Mes
                                DATA      ;Put Mes in Data Spc
0000" 48 69 20  MSG     DB  'Hi There'; Generate Mesg
                                PROG        ;Return to CSEG
0006' C9                RET              ;End of Subroutine.
```

The data string actually will be located elsewhere at link time, and the RET instruction will be just after the CALL OUTPUT. The Program segment is usually used for program or machine code. This pseudo-op takes no parameters, and is illegal in absolute mode.

DATA
DSEG

Select Data Segment Loading Counter. This pseudo-op is normally used for generating data to be loaded at another area in the target machine. It is also useful for defining address space in RAM away from the code area in PROM. The loading counter and logical PC selected is the one from the last used DATA area. For example, if this code followed the code above, look what would be generated.

```

                                DSEG        ;define addresses in
0008"          LBL1          DS  1          ;RAM storage
0009"          LBL2          DS  10         ;more RAM storage
```

The actual load location for this address space is selected at link time with the /D or /A option. The DSEG address space is usually used for data storage. This pseudo-op takes no parameters, and is illegal in absolute mode.

COM /COMNAME/
COMMON /COMNAME/

Common Block. This pseudo-op selects the named common block for the new code type. The block name, like other symbols, is significant to the first 16 characters internally, to 16 externally in SLR Format, 7 in M-REL format.

Unlike PROG and DATA address spaces, common areas are not different in each module. For example, the first byte in the PROG area for module 1 will be at a different physical address than the first byte in the PROG area for module 2. With Common blocks, the address spaces are the same to each module, which allows access to the same data space from different modules.

The actual physical address of the common blocks is selected at link time with the /C or /A option.

This pseudo-op is illegal in absolute mode.

.PHASE <EXP>

Select Logical PC. This pseudo-op selects a new logical program counter, without changing the load counter. It is useful for generating code at the current location for later transfer and execution at location <EXP>. This pseudo-op is valid in any mode, and <EXP> can evaluate to an absolute or relative value. Once inside a .PHASE block, all PC maintenance pseudo-ops are illegal until the next .DEPHASE pseudo-op is encountered, which brings us to another point.

.DEPHASE

End of Logical Phase Block. This pseudo-op terminates the current .PHASE block. For example,

		ORG 100H	
0100 21 010E		LD HL,RETT	;Return Instr Physical
0103 11 2000		LD DE,DESTIN	;Return Instr Destination
0106 01 0001		LD BC,1	;Return Instr Length
0109 ED B0		LDIR	;Move it
010B 21 2000		JP DESTIN	;Jump to It
	RETT	.PHASE 2000H	;Actual Execution addr
2000 C9	DESTIN	RET	;Generated at 010E with
		.DEPHASE	;Logical address of 2000H

Phase blocks may not be nested.

2. DATA DEFINITION AND GENERATION

This sections contains the pseudo-ops that are involved in defining and generating all types of data.

```

DB    [EXP1][,EXP2]
DEFB [EXP1][,EXP2]
DEFM [EXP1][,EXP2]

```

Define Byte. This pseudo-op allows the generation of bytes of data. Data can be a single expression or string, or several separated by commas. In relocatable mode, the expressions may be absolute, relative, or relocatable. Note that a null item will generate no output, nor is it a syntax error. This is to accomodate missing parameters in macro expansions. For example,

```

0100 00 01 02 03  NUMS  DEFB      0,1,2,,,3

```

and

```

0104 40 ?? 02 48          DB      40H,LOW EXTERN1,'B'&1FH,'Hi'

```

are legal statements.

```

DW    [EXP1][,EXP2]
DEFW [EXP1][,EXP2]

```

Define Word. This pseudo-op is used to generate 16-bit quantities, low byte first. Data can be a single expression or string, or several separated by commas. In relocatable mode, the expressions may be absolute, relative, or relocatable. Note that a null item will generate no output, nor is it a syntax error. This is to accomodate missing parameters in macro expansions. For example, the following are legal statements:

```

0100 0100  ???  START  DEFW      START,EXTERNAL SHR  4
0104 69 48  54 20      DW      'Hi There'

```

DS <EXP1>[,<EXP2>]
DEFS <EXP1>[,<EXP2 >]

Define Space. This pseudo-op is used to allocate address space for variable storage or whatever. The address counter is incremented by <EXP1>, which must evaluate to an absolute value on the first pass. No code or data is generated to fill the address space skipped unless the optional <EXP2> is specified. <EXT2> is used to fill the declared space with a byte value. Note that <EXT2> does not need to be defined at assembly time. Note also that during COM file generation, if <EXP2> is missing, the space is filled with zeros. For example,

```
BUFA      DEFS      200H      ;Room for 512 byte buffer
```

declares a buffer BUFA with a size of 512 bytes. In HEX or REL mode, the initial contents of this buffer are not defined. On the other hand,

```
BUFA:     DS        200H,EMPTY ;Room for 512 byte buffer
```

declares the same buffer, but its contents are initialized to EMPTY, which possibly won't be defined until link time. The colon after the label is optional unless the label is a reserved word, or is also used as a macro name.

<LABEL> **EQU** <EXP>

Equate Directive. This pseudo-op declares a value <EXP> to be assigned to a label. <EXP> must evaluate to an absolute or relative item by the second pass. The label being defined must not have been previously defined. For example, the following statements

```
FALSE     EQU       0           ;false is 0
TRUE:     EQU       NOT FALSE ;true is ffff
```

assign values to symbols TRUE and FALSE. The colon after the label is optional in all cases.

<LABEL> **DEFL** <EXP>
 <LABEL> **ASET** <EXP>

Define Label. This pseudo-op is identical to EQU except that it can be used to redefine a label that has been previously defined. For instance, it could be used to update a counter:

```
COUNT     DEFL      COUNT+1    ;increment count
```

```
EXT          LABEL1[,LABEL2]
EXTRN        LABEL1[,LABEL2]
EXTERNAL     LABEL1[,LABEL2]
BYTE EXT      LABEL1[,LABEL2]
BYTE EXTRN    LABEL1[,LABEL2]
BYTE EXTERNAL LABEL1[,LABEL2]
```

External Declaration. This pseudo-op tells the assembler that the symbols in this list are not defined in this module, but are defined in another module, to be resolved at link time. Valid only in relocatable mode, this pseudo-op is necessary only if you don't use the /U option in your command line.

Symbols may also be declared external by following them by two pound-signs (##) when they are referenced. For example,

```
LD      BC,EXTERNAL##
```

declares EXTERNAL to be an external.

```
ENT          <LABELIST>
ENTRY        <LABELIST>
GLOBAL       <LABELIST>
PUBLIC        <LABELIST>
```

Entry Point Declaration. This pseudo-op tells the assembler to make this list of symbols and their values available to the linker so that they may be referenced as EXTERNALs from other modules. This is not allowed in absolute mode.

```
PUBLIC     LABEL1,LABEL2,LABEL3
```

Entry points may also be defined by following the symbol by two colons (::) when the symbol is defined.

```
LABEL1::    LD      A,3
LABEL2::    EQU     $
```

declares LABEL1 and LABEL2 as globals.

Symbols declared public must be defined on the first pass when generating SLR Format output.

.ACCEPT [STRING,]<SYMBOL>

The .ACCEPT pseudo-op is used to request a value for a symbol from the console. <SYMBOL> is a valid symbol name not elsewhere defined in the file. **Z80ASM** will print the optional STRING on the console, or if no STRING is given then the <SYMBOL> name, followed by a '?', and wait for the value. The value must be a valid expression, defined on the first pass (you can use symbols already defined). For example,

```
.accept  DEBUG_FLAG
```

will cause Z80ASM to print

```
DEBUG_FLAG ?
```

on the console. At this point you type a valid expression. If TRUE has already been defined, you could type

```
DEBUG_FLAG ? NOT TRUE
```

to set DEBUG_FLAG to false.

Since console buffer read is used, you can supply your input through a submit file.

Only one <SYMBOL> can be used per .ACCEPT statement.

```
DEFC      EXP1[,EXP2]
DC        EXP1[,EXP2]
```

The DEFC pseudo-op is used to generate strings that terminate with the high bit (bit 7) set. The <EXP>'s may be strings or valid byte data:

```
DEFC      "This terminates at the LF',0dh,0ah
```

In this case the 0ah is converted to an 8ah.

```
DEFZ      EXP1[,EXP2]
```

The DEFZ pseudo-op is also used in generating data strings, but this one terminates with an extra zero byte.

```
DEFZ      'hi'
```

generates 68H,69H,00H.

3. CONDITIONAL ASSEMBLY

This section describes the facility whereby sections of code may be selected for assembly based on certain conditions.

One very useful way to utilize conditional assembly is in program debugging. For instance, you can insert code to print out intermediate values of variables, or messages to say where the program is, etc. By putting all that code in conditional assembly blocks, you would not have to delete the code after debugging, or re-insert it when something else crops up. You could just define a symbol `DEBUG` at the top of the module that defines whether or not the debug code is included in the assembled code. The following pseudo-ops allow conditional assembly.

NOTE: For any of the IF-type pseudo-ops that take an expression as a parameter, `CONFIG` can be used to select whether to look at just bit 0 (for DRI compatibility) or the whole 16-bit value.

IF <EXP>
COND <EXP>
IFT <EXP>

Conditional Assembly. This pseudo-op allows conditional assembly of a section of code. For instance, if you have code that you want assembled only during program debugging, you could use the statement

```
IF          DEBUG
```

to tell **Z80ASM** whether the following code should be assembled. If the expression <EXP> evaluates to an absolute zero, then the subsequent code up to the next active ELSE or ENDIF is not assembled. A non-zero value yields a true IF condition, causing the subsequent lines to be assembled. Since IF blocks may be nested, active means on the same nest level.

The expression must yield a defined absolute result on the first pass.

Conditional blocks may be nested as deeply as you need (theoretically to 65535 levels...).

IFE <EXP>
IFF <EXP>

This pseudo-op has the opposite effect of the IF pseudo-op. If the given expression evaluates to 0, a true IF condition is generated.

ENDIF
ENDC

Endif directive. This pseudo-op declares the end of the last conditional block declared.

ELSE

Else directive. This pseudo-op toggles the current IF condition. If the current IF condition is false, now it is true, and vice versa. For example,

```
PRNTOUT ;call printer output routine
IF      PARPNT      ;if parallel printer
CALL    PAROUT      ;call parallel output
ELSE    ;otherwise
CALL    SEROUT      ;call serial output
ENDIF   ;terminate if block
```

if PARPNT is true, the first call will be assembled, otherwise the second one will be used.

IF0

This pseudo-op is a special form of the IF pseudo-op. It takes no parameters, but assembles the following lines of code only in one-pass mode assemblies.

IF1

This is similar to the IF0 pseudo-op, except that it returns a true conditional only on pass 1 of 2-pass mode.

IF2

This is similar to the IF1 pseudo-op, except that it returns a true conditional only on pass 2 of 2-pass mode.

IFDEF <SYMBOL>

The IFDEF pseudo-op takes a valid symbol as an operand, and assembles the following lines of code only if the symbol has been defined in the module as absolute, relative or external.

IFNDEF <SYMBOL>

The IFNDEF pseudo-op performs the opposite function as IFDEF. The conditional block is assembled only if the given symbol is undefined.

IFIDN <PARAM1>,<PARAM2>

The IFIDN pseudo-op assembles the conditional block only if the character strings (not necessarily valid STRINGS) passed as PARAM1 and PARAM2 are identical. This is useful in testing macro parameters. Note that the angle bracket delimiters are required.

IFDIF <PARAM1>,<PARAM2>

The IFDIF pseudo-op performs the opposite function of IFIDN, the parameters must be different to assemble the conditional block. Note that the angle bracket delimiters are required.

IFB <PARAM>

IF BLANK. If the parameter passed is blank, a true IF is generated. This can be used to test for the existence of macro parameters. The CONFIG program can be used to select whether or not a space is treated as a blank parameter (ignore leading spaces). Note that the angle bracket delimiters are required.

IFNB <PARAM >

Opposite of IFB. IF NOT BLANK. Note that the angle bracket delimiters are required.

4. MACRO FACILITY

Macro facilities provide the ability to reproduce sequences of instructions repetitively and simply. **Z80ASM** supports the Intel standard macro facility, which includes several different types of macros.

The simplest form of macros are the inline macro types, REPT, IRP, and IRPC. These all store source lines for immediate repetition after which the lines are discarded.

```
[LABEL]    REPT      <EXP>
```

Repeat Macro. The repeat macro reads a group of statements up to the next matching ENDM or MEND pseudo-op. That is the BODY of the macro. The group of statements are then scanned and assembled <EXP> times. <EXP> must be defined and absolute on the first pass.

The body of the REPT macro may contain other proper macro definitions including other REPT macros. The body can also contain nested conditional pseudo-ops. Any active conditionals are automatically terminated at the end of each repetition of the macro, so that IF and ELSE directives are not required to have their matching ENDIF statements if they begin within the macro body.

In the following example we use the REPT macro to build a table of bytes from 20 to 0.

```

0014      1 ??VAR  DEFL  20      ;set initial value
          2      REPT  21      ;repeat 21 times
          3      DEFB  ??VAR    ;generate the byte
          4 ??VAR  DEFL  ??VAR-1 ;decrement the var
          5      ENDM          ;end of macro body
0100  14      A    1      DEFB  ??VAR    ;generate the byte
0101  13      A    1      DEFB  ??VAR    ;generate the byte
0102  12      A    1      DEFB  ??VAR    ;generate the byte
0103  11      A    1      DEFB  ??VAR    ;generate the byte
0104  10      A    1      DEFB  ??VAR    ;generate the byte
0105  0F      A    1      DEFB  ??VAR    ;generate the byte
0106  0E      A    1      DEFB  ??VAR    ;generate the byte
0107  0D      A    1      DEFB  ??VAR    ;generate the byte
0108  0C      A    1      DEFB  ??VAR    ;generate the byte
0109  0B      A    1      DEFB  ??VAR    ;generate the byte
010A  0A      A    1      DEFB  ??VAR    ;generate the byte
010B  09      A    1      DEFB  ??VAR    ;generate the byte
010C  08      A    1      DEFB  ??VAR    ;generate the byte
010D  07      A    1      DEFB  ??VAR    ;generate the byte
010E  06      A    1      DEFB  ??VAR    ;generate the byte
010F  05      A    1      DEFB  ??VAR    ;generate the byte
0110  04      A    1      DEFB  ??VAR    ;generate the byte
0111  03      A    1      DEFB  ??VAR    ;generate the byte
0112  02      A    1      DEFB  ??VAR    ;generate the byte
0113  01      A    1      DEFB  ??VAR    ;generate the byte
0114  00      A    1      DEFB  ??VAR    ;generate the byte

```

[LABEL] **IRPC** <DUMMY>,<CHARLIST>

Indefinite Repeat Character. The IRPC macro reads the body of the macro, just like the REPT macro. The body of the macro is then scanned and assembled once for each character in the given CHARLIST. However, any occurrence of the item DUMMY in the body is replaced by the current character in CHARLIST. Well, almost any occurrence. See the section on dummy parameter evaluation.

As with the REPT macro, this can contain nested macros and conditionals.

In the next example, we use an IRPC macro to generate a string of characters, each with the high bit set to 1. Note that the DUMMY parameter XX is replaced by a single character for each iteration of the macro. Note also that an ampersand must be used in front of or after the DUMMY in order for it to be replaced within a quoted string.

Note also that comments started with two semi-colons are not stored with the macro, and therefore 1.) don't take up memory space, and 2.) don't appear in the expansion.

			1	IRPC	XX,MESSAGE1	;set hi bit of each
			2	DB	'&XX'+80H	;;this comment gone
			3	ENDM		
0100	CD	A	1	DB	'M'+80H	
0101	C5	A	1	DB	'E'+80H	
0102	D3	A	1	DB	'S'+80H	
0103	D3	A	1	DB	'S'+80H	
0104	C1	A	1	DB	'A'+80H	
0105	C7	A	1	DB	'G'+80H	
0106	C5	A	1	DB	'E'+80H	
0107	B1	A	1	DB	'1'+80H	

```
[LABEL]   IRP      < DUMMY >,<<PARAMLIST>>
```

Indefinite Repeat. The IRP is very similar to the IRPC, except that the parameters are multi-character items. Note that the brackets around the PARAMLIST are required.

In the following example, we generate four error messages with labels. Note that the label is constructed by "concatenating" the letter M to the parameter. The ampersand (&) is used to do that.

```

                                1      mtlist
                                2      IRP      XX,<MACRO,.PHASE,IF,.DEPHASE>
                                3 XX&M:  DEFB      'missing &XX',0DH,0Ah
                                4      ENDM
0100  6D 69 73 73A 1 MACROM: DEFB      'missing MACRO',0DH,0Ah
0104  69 6E 67 20A 1
0108  4D 41 43 52A 1
010C  4F 0D 0A   A 1
010F  6D 69 73 73A 1 .PHASEM: DEFB      'missing .PHASE',0DH,0Ah
0113  69 6E 67 20A 1
0117  2E 50 48 41A 1
011B  53 45 0D 0AA 1
011F  6D 69 73 73A 1 IFM:      DEFB      'missing IF',0DH,0Ah
0123  69 6E 67 20A 1
0127  49 46 0D 0AA 1
012B  6D 69 73 73A 1 .DEPHASEM: DEFB 'missing .DEPHASE',0DH,0Ah
012F  69 6E 67 20A 1
0133  2E 44 45 50A 1
0137  48 41 53 45A 1
013B  0D 0A   A   1
                                5
```

<LABEL> **MACRO** [<DUMMYLIST>]

Macro Definition. This is the most sophisticated form of macro item. This statement declares the beginning of a MACRO definition. The <LABEL> must be present; it is the name by which the macro will be referred to later. It follows the same rules as labels. A colon after the label is optional.

The <DUMMYLIST> is optional. If present, it declares <dummy> items which will be replaced by other items when the macro is called. Multiple <dummy> items are separated by commas. <Dummy> items follow the same rules as labels.

All source lines following the macro header are stored in memory under the name <LABEL>, up to the next matching ENDM or MEND. Since macros may contain macro definitions (nested macro definitions), matching means the ENDM at the same nest level.

To call the macro, just use the macro name as you would any other opcode or pseudo-op, passing with it any desired parameters.

Suppose you are writing a program for CP/M systems in which you do a lot of displaying messages on the console. It might be nice to design a macro that would let you easily do that. You could then call the PRINT macro to print a string on the screen. For example,

```

                                1      .LALL
                                2 PRINT  MACRO  XX
                                3          LD      DE,STRING
                                4          LD      C,9
                                5          CALL    5
                                6          JP      STEND
                                7 STRING  DEFB    XX,0DH,0AH,'$'
                                8 STEND
                                9          ENDM
                                10         PRINT  'This is a test'
0100 11 010B A 1          LD      DE,STRING
0103 OE 09 A 2          LD      C,9
0105 CD 0005 A 3          CALL    5
0108 C3 011C A 4          JP      STEND
010B 54 68 69 73A 5 STRING  DEFB    'This is a test',0DH,0AH,'$'
011C A 6 STEND
                                11

```

The line `PRINT 'This is a test'` generated the next 6 lines of macro output, to set up the data and system call to output the string on the console. But there is a problem. If the `PRINT` macro had been called again, the labels `STRING` and `STEND` would have been multiply defined, which is illegal (you won't go to jail, your program just won't assemble).

One way around that would be to pass another parameter to `concat` to the labels, to make them unique. **Z80ASM** provides another way, which will be discussed next.

LOCAL <LABELIST>

Local Labels. This pseudo-op declares a label or set of labels to be local to the current macro expansion, i.e., each time the macro is expanded or repeated, generate a unique label for each of these. The labels in <LABELIST> must be legal labels. The `LOCAL` statement should occur before the labels are referenced in the macro.

Z80ASM implements `LOCAL` labels by generating a unique label for each `LOCAL` consisting of two question marks followed by 4 hexadecimal digits. For example, the first `LOCAL` label encountered in an assembly would be replaced by the label `??0001`. Therefore, you should avoid the use of labels that have that form in order to lessen the chances of confusion.

`LOCAL` label replacement is done at expansion time, not at macro definition time. This implies that parameters passed to a macro that match a local symbol name will also be replaced by a local label.

Note that `LOCAL` labels are valid in all macro types.


```

1          .LALL
2 PRINT    MACRO    XX
3          LOCAL    STRING,STEND
4          LD        DE,STRING
5          LD        C, 9
6          CALL      5
7          JP        STEND
8 STRING    DEFB     XX,0DH,0AH,'$'
9 STEND     ENDM
10         PRINT    'This is a test'
11         A        1
12         A        2
13         A        3
14         A        4
15         A        5
16         A        6
17         A        7
18         A        8
19         A        9
20         A        10
21         A        11
22         A        12
23         A        13
24         A        14
25         A        15
26         A        16
27         A        17
28         A        18
29         A        19
30         A        20
31         A        21
32         A        22
33         A        23
34         A        24
35         A        25
36         A        26
37         A        27
38         A        28
39         A        29
40         A        30
41         A        31
42         A        32
43         A        33
44         A        34
45         A        35
46         A        36
47         A        37
48         A        38
49         A        39
50         A        40
51         A        41
52         A        42
53         A        43
54         A        44
55         A        45
56         A        46
57         A        47
58         A        48
59         A        49
60         A        50
61         A        51
62         A        52
63         A        53
64         A        54
65         A        55
66         A        56
67         A        57
68         A        58
69         A        59
70         A        60
71         A        61
72         A        62
73         A        63
74         A        64
75         A        65
76         A        66
77         A        67
78         A        68
79         A        69
80         A        70
81         A        71
82         A        72
83         A        73
84         A        74
85         A        75
86         A        76
87         A        77
88         A        78
89         A        79
90         A        80
91         A        81
92         A        82
93         A        83
94         A        84
95         A        85
96         A        86
97         A        87
98         A        88
99         A        89
100        A        90
101        A        91
102        A        92
103        A        93
104        A        94
105        A        95
106        A        96
107        A        97
108        A        98
109        A        99
110        A        100
111        A        101
112        A        102
113        A        103
114        A        104
115        A        105
116        A        106
117        A        107
118        A        108
119        A        109
120        A        110
121        A        111
122        A        112
123        A        113
124        A        114
125        A        115
126        A        116
127        A        117
128        A        118
129        A        119
130        A        120
131        A        121
132        A        122
133        A        123
134        A        124
135        A        125
136        A        126
137        A        127
138        A        128
139        A        129
140        A        130
141        A        131
142        A        132
143        A        133
144        A        134
145        A        135
146        A        136
147        A        137
148        A        138
149        A        139
150        A        140
151        A        141
152        A        142
153        A        143
154        A        144
155        A        145
156        A        146
157        A        147
158        A        148
159        A        149
160        A        150
161        A        151
162        A        152
163        A        153
164        A        154
165        A        155
166        A        156
167        A        157
168        A        158
169        A        159
170        A        160
171        A        161
172        A        162
173        A        163
174        A        164
175        A        165
176        A        166
177        A        167
178        A        168
179        A        169
180        A        170
181        A        171
182        A        172
183        A        173
184        A        174
185        A        175
186        A        176
187        A        177
188        A        178
189        A        179
190        A        180
191        A        181
192        A        182
193        A        183
194        A        184
195        A        185
196        A        186
197        A        187
198        A        188
199        A        189
200        A        190
201        A        191
202        A        192
203        A        193
204        A        194
205        A        195
206        A        196
207        A        197
208        A        198
209        A        199
210        A        200
211        A        201
212        A        202
213        A        203
214        A        204
215        A        205
216        A        206
217        A        207
218        A        208
219        A        209
220        A        210
221        A        211
222        A        212
223        A        213
224        A        214
225        A        215
226        A        216
227        A        217
228        A        218
229        A        219
230        A        220
231        A        221
232        A        222
233        A        223
234        A        224
235        A        225
236        A        226
237        A        227
238        A        228
239        A        229
240        A        230
241        A        231
242        A        232
243        A        233
244        A        234
245        A        235
246        A        236
247        A        237
248        A        238
249        A        239
250        A        240
251        A        241
252        A        242
253        A        243
254        A        244
255        A        245
256        A        246
257        A        247
258        A        248
259        A        249
260        A        250
261        A        251
262        A        252
263        A        253
264        A        254
265        A        255
266        A        256
267        A        257
268        A        258
269        A        259
270        A        260
271        A        261
272        A        262
273        A        263
274        A        264
275        A        265
276        A        266
277        A        267
278        A        268
279        A        269
280        A        270
281        A        271
282        A        272
283        A        273
284        A        274
285        A        275
286        A        276
287        A        277
288        A        278
289        A        279
290        A        280
291        A        281
292        A        282
293        A        283
294        A        284
295        A        285
296        A        286
297        A        287
298        A        288
299        A        289
300        A        290
301        A        291
302        A        292
303        A        293
304        A        294
305        A        295
306        A        296
307        A        297
308        A        298
309        A        299
310        A        300
311        A        301
312        A        302
313        A        303
314        A        304
315        A        305
316        A        306
317        A        307
318        A        308
319        A        309
320        A        310
321        A        311
322        A        312
323        A        313
324        A        314
325        A        315
326        A        316
327        A        317
328        A        318
329        A        319
330        A        320
331        A        321
332        A        322
333        A        323
334        A        324
335        A        325
336        A        326
337        A        327
338        A        328
339        A        329
340        A        330
341        A        331
342        A        332
343        A        333
344        A        334
345        A        335
346        A        336
347        A        337
348        A        338
349        A        339
350        A        340
351        A        341
352        A        342
353        A        343
354        A        344
355        A        345
356        A        346
357        A        347
358        A        348
359        A        349
360        A        350
361        A        351
362        A        352
363        A        353
364        A        354
365        A        355
366        A        356
367        A        357
368        A        358
369        A        359
370        A        360
371        A        361
372        A        362
373        A        363
374        A        364
375        A        365
376        A        366
377        A        367
378        A        368
379        A        369
380        A        370
381        A        371
382        A        372
383        A        373
384        A        374
385        A        375
386        A        376
387        A        377
388        A        378
389        A        379
390        A        380
391        A        381
392        A        382
393        A        383
394        A        384
395        A        385
396        A        386
397        A        387
398        A        388
399        A        389
400        A        390
401        A        391
402        A        392
403        A        393
404        A        394
405        A        395
406        A        396
407        A        397
408        A        398
409        A        399
410        A        400
411        A        401
412        A        402
413        A        403
414        A        404
415        A        405
416        A        406
417        A        407
418        A        408
419        A        409
420        A        410
421        A        411
422        A        412
423        A        413
424        A        414
425        A        415
426        A        416
427        A        417
428        A        418
429        A        419
430        A        420
431        A        421
432        A        422
433        A        423
434        A        424
435        A        425
436        A        426
437        A        427
438        A        428
439        A        429
440        A        430
441        A        431
442        A        432
443        A        433
444        A        434
445        A        435
446        A        436
447        A        437
448        A        438
449        A        439
450        A        440
451        A        441
452        A        442
453        A        443
454        A        444
455        A        445
456        A        446
457        A        447
458        A        448
459        A        449
460        A        450
461        A        451
462        A        452
463        A        453
464        A        454
465        A        455
466        A        456
467        A        457
468        A        458
469        A        459
470        A        460
471        A        461
472        A        462
473        A        463
474        A        464
475        A        465
476        A        466
477        A        467
478        A        468
479        A        469
480        A        470
481        A        471
482        A        472
483        A        473
484        A        474
485        A        475
486        A        476
487        A        477
488        A        478
489        A        479
490        A        480
491        A        481
492        A        482
493        A        483
494        A        484
495        A        485
496        A        486
497        A        487
498        A        488
499        A        489
500        A        490
501        A        491
502        A        492
503        A        493
504        A        494
505        A        495
506        A        496
507        A        497
508        A        498
509        A        499
510        A        500
511        A        501
512        A        502
513        A        503
514        A        504
515        A        505
516        A        506
517        A        507
518        A        508
519        A        509
520        A        510
521        A        511
522        A        512
523        A        513
524        A        514
525        A        515
526        A        516
527        A        517
528        A        518
529        A        519
530        A        520
531        A        521
532        A        522
533        A        523
534        A        524
535        A        525
536        A        526
537        A        527
538        A        528
539        A        529
540        A        530
541        A        531
542        A        532
543        A        533
544        A        534
545        A        535
546        A        536
547        A        537
548        A        538
549        A        539
550        A        540
551        A        541
552        A        542
553        A        543
554        A        544
555        A        545
556        A        546
557        A        547
558        A        548
559        A        549
560        A        550
561        A        551
562        A        552
563        A        553
564        A        554
565        A        555
566        A        556
567        A        557
568        A        558
569        A        559
570        A        560
571        A        561
572        A        562
573        A        563
574        A        564
575        A        565
576        A        566
577        A        567
578        A        568
579        A        569
580        A        570
581        A        571
582        A        572
583        A        573
584        A        574
585        A        575
586        A        576
587        A        577
588        A        578
589        A        579
590        A        580
591        A        581
592        A        582
593        A        583
594        A        584
595        A        585
596        A        586
597        A        587
598        A        588
599        A        589
600        A        590
601        A        591
602        A        592
603        A        593
604        A        594
605        A        595
606        A        596
607        A        597
608        A        598
609        A        599
610        A        600
611        A        601
612        A        602
613        A        603
614        A        604
615        A        605
616        A        606
617        A        607
618        A        608
619        A        609
620        A        610
621        A        611
622        A        612
623        A        613
624        A        614
625        A        615
626        A        616
627        A        617
628        A        618
629        A        619
630        A        620
631        A        621
632        A        622
633        A        623
634        A        624
635        A        625
636        A        626
637        A        627
638        A        628
639        A        629
640        A        630
641        A        631
642        A        632
643        A        633
644        A        634
645        A        635
646        A        636
647        A        637
648        A        638
649        A        639
650        A        640
651        A        641
652        A        642
653        A        643
654        A        644
655        A        645
656        A        646
657        A        647
658        A        648
659        A        649
660        A        650
661        A        651
662        A        652
663        A        653
664        A        654
665        A        655
666        A        656
667        A        657
668        A        658
669        A        659
670        A        660
671        A        661
672        A        662
673        A        663
674        A        664
675        A        665
676        A        666
677        A        667
678        A        668
679        A        669
680        A        670
681        A        671
682        A        672
683        A        673
684        A        674
685        A        675
686        A        676
687        A        677
688        A        678
689        A        679
690        A        680
691        A        681
692        A        682
693        A        683
694        A        684
695        A        685
696        A        686
697        A        687
698        A        688
699        A        689
700        A        690
701        A        691
702        A        692
703        A        693
704        A        694
705        A        695
706        A        696
707        A        697
708        A        698
709        A        699
710        A        700
711        A        701
712        A        702
713        A        703
714        A        704
715        A        705
716        A        706
717        A        707
718        A        708
719        A        709
720        A        710
721        A        711
722        A        712
723        A        713
724        A        714
725        A        715
726        A        716
727        A        717
728        A        718
729        A        719
730        A        720
731        A        721
732        A        722
733        A        723
734        A        724
735        A        725
736        A        726
737        A        727
738        A        728
739        A        729
740        A        730
741        A        731
742        A        732
743        A        733
744        A        734
745        A        735
746        A        736
747        A        737
748        A        738
749        A        739
750        A        740
751        A        741
752        A        742
753        A        743
754        A        744
755        A        745
756        A        746
757        A        747
758        A        748
759        A        749
760        A        750
761        A        751
762        A        752
763        A        753
764        A        754
765        A        755
766        A        756
767        A        757
768        A        758
769        A        759
770        A        760
771        A        761
772        A        762
773        A        763
774        A        764
775        A        765
776        A        766
777        A        767
778        A        768
779        A        769
780        A        770
781        A        771
782        A        772
783        A        773
784        A        774
785        A        775
786        A        776
787        A        777
788        A        778
789        A        779
790        A        780
791        A        781
792        A        782
793        A        783
794        A        784
795        A        785
796        A        786
797        A        787
798        A        788
799        A        789
800        A        790
801        A        791
802        A        792
803        A        793
804        A        794
805        A        795
806        A        796
807        A        797
808        A        798
809        A        799
810        A        800
811        A        801
812        A        802
813        A        803
814        A        804
815        A        805
816        A        806
817        A        807
818        A        808
819        A        809
820        A        810
821        A        811
822        A        812
823        A        813
824        A        814
825        A        815
826        A        816
827        A        817
828        A        818
829        A        819
830        A        820
831        A        821
832        A        822
833        A        823
834        A        824
835        A        825
836        A        826
837        A        827
838        A        828
839        A        829
840        A        830
841        A        831
842        A        832
843        A        833
844        A        834
845        A        835
846        A        836
847        A        837
848        A        838
849        A        839
850        A        840
851        A        841
852        A        842
853        A        843
854        A        844
855        A        845
856        A        846
857        A        847
858        A        848
859        A        849
860        A        850
861        A        851
862        A        852
863        A        853
864        A        854
865        A        855
866        A        856
867        A        857
868        A        858
869        A        859
870        A        860
871        A        861
872        A        862
873        A        863
874        A        864
875        A        865
876        A        866
877        A        867
878        A        868
879        A        869
880        A        870
881        A        871
882        A        872
883        A        873
884        A        874
885        A        875
886        A        876
887        A        877
888        A        878
889        A        879
890        A        880
891        A        881
892        A        882
893        A        883
894        A        884
895        A        885
896        A        886
897        A        887
898        A        888
899        A        889
900        A        890
901        A        891
902        A        892
903        A        893
904        A        894
905        A        895
906        A        896
907        A        897
908        A        898
909        A        899
910        A        900
911        A        901
912        A        902
913        A        903
914        A        904
915        A        905
916        A        906
917        A        907
918        A        908
919        A        909
920        A        910
921        A        911
922        A        912
923        A        913
924        A        914
925        A        915
926        A        916
927        A        917
928        A        918
929        A        919
930        A        920
931        A        921
932        A        922
933        A        923
934        A        924
935        A        925
936        A        926
937        A        927
938        A        928
939        A        929
940        A        930
941        A        931
942        A        932
943        A        933
944        A        934
945        A        935
946        A        936
947        A        937
948        A        938
949        A        939
950        A        940
951        A        941
952        A        942
953        A        943
954        A        944
955        A        945
956        A        946
957        A        947
958        A        948
959        A        949
960        A        950
961        A        951
962        A        952
963        A        953
964        A        954
965        A        955
966        A        956
967        A        957
968        A        958
969        A        959
970        A        960
971        A        961
972        A        962
973        A        963
974        A        964
975        A        965
976        A        966
977        A        967
978        A        968
979        A        969
980        A        970
981        A        971
982        A        972
983        A        973
984        A        974
985        A        975
986        A        976
987        A        977
988        A        978
989        A        979
990        A        980
991        A        981
992        A        982
993        A        983
994        A        984
995        A        985
996        A        986
997        A        987
998        A        988
999        A        989
1000       A        990
1001       A        991
1002       A        992
1003       A        993
1004       A        994
1005       A        995
1006       A        996
1007       A        997
1008       A        998
1009       A        999
1010       A        1000
1011       A        1001
1012       A        1002
1013       A        1003
1014       A        1004
1015       A        1005
1016       A        1006
1017       A        1007
1018       A        1008
1019       A        1009
1020       A        1010
1021       A        1011
1022       A        1012
1023       A        1013
1024       A        1014
1025       A        1015
1026       A        1016
1027       A        1017
1028       A        1018
1029       A        1019
1030       A        1020
1031       A        1021
1032       A        1022
1033       A        1023
1034       A        1024
1035       A        1025
1036       A        1026
1037       A        1027
1038       A        1028
1039       A        1029
1040       A        1030
1041       A        1031
1042       A        1032
1043       A        1033
1044       A        1034
1045       A        1035
1046       A        1036
1047       A        1037
1048       A        1038
1049       A        1039
1050       A        1040
1051       A        1041
1052       A        1042
1053       A        1043
1054       A        1044
1055       A        1045
1056       A        1046
1057       A        1047
1058       A        1048
1059       A        1049
1060       A        1050
1061       A        1051
1062       A        1052
1063       A        1053
1064       A        1054
1065       A        1055
1066       A        1056
1067       A        1057
1068       A        1058
1069       A        1059
1070       A        1060
1071       A        1061
1072       A        1062
1073       A        1063
1074       A        1064
1075       A        1065
1076       A        1066
1077       A        1067
1078       A        1068
1079       A        1069
1080       A        1070
1081       A        1071
1082       A        1072
1083       A        1073
1084       A        1074
1085       A        1075
1086       A        1076
1087       A        1077
1088       A        1078
1089       A        1079
1090       A        1080
1091       A        1081
1092       A        1082
1093       A        1083
1094       A        1084
1095       A        1085
1096       A        1086
1097       A        1087
1098       A        1088
1099       A        1089
1100       A        1090
1101       A        1091
1102       A        1092
1103       A        1093
1104       A        1094
1105       A        1095
1106       A        1096
1107       A        1097
1108       A        1098
1109       A        1099
1110       A        1100
1111       A        1101
1112       A        1102
1113       A        1103
1114       A        1104
1115       A        1105
1116       A        1106
1
```

EXITM

Exit macro expansion. This pseudo-op allows an easy way to terminate a macro expansion. It is usually used in conjunction with a conditional test.

EXITM is also allowed in an include file or maclib file, to halt the processing of those files.

Note that EXITM exits only a macro expansion, not a definition. Use ENDM or MEND to end the macro definition.

INCLUDE <FILENAME.EXT>
\$INCLUDE <FILENAME.EXT>

Include another source file. This pseudo-op takes as an argument a valid CP/M file name. That disk file is then opened and inserted at the point. Note that your listing line numbers start over at 1, and that a letter precedes that number. That is the nesting level. Any errors generated while processing this included file will give the Included file name and line number in that file. Note also that the included file can also contain an INCLUDE directive. At the end of the included file, assembly continues at the previous file, next line. This is a very powerful feature for including common macro definitions, and even assembling large projects without resorting to relocatable code.

MACLIB <FILENAME.EXT>

Include Macro Definition File. This pseudo-op is identical to an INCLUDE, except that it is ignored on the second pass. This pseudo-op is used to read macro definition files, or any source files that produce no output code. This is to save time on 2-pass assemblies since the whole MACLIB file will be skipped on the second pass.

Dummy Parameter Evaluation

While reading the body of a macro, **Z80ASM** looks for the occurrence of any of the optional dummy parameters in the text. There are several rules that are followed.

1. Dummy parameters are not replaced in a comment field.
2. A dummy parameter delimited by spaces, tabs, commas, etc., and not inside a quoted string, is automatically flagged for replacement at expansion time.
3. Any dummy parameter preceded or followed by an ampersand (&), whether or not it is contained in a quoted string, is flagged for replacement, and the leading and/or trailing ampersand is removed. This is useful for dummy replacement in strings, and also for concatenating a parameter to something else.
4. Any dummy parameter preceded by an up-arrow (^) is ignored. The up-arrow is used to cause a character to be taken literally, i.e., an up-arrow can be represented as two up-arrows in succession.

Parameter Evaluation Rules

There are a number of special options available to the programmer when it comes to parameter passing. Here we will describe the rules that **Z80ASM** follows when evaluating parameters.

First, all leading blanks are skipped. In other words, the parameter starts at the first non-blank character. That first non-blank character determines what type of parameter is being evaluated.

If the first character is a quotation mark (single or double), then the parameter is processed as a STRING, following the rules for strings. The leading and trailing quotation marks are passed as part of the parameter.

If the first character is a '<' (less-than sign, referred to in this discussion as a left bracket), then the '<' is removed, and the text is processed up to the next matching '>'. By matching we mean that the brackets are nestable, so that if there are three left brackets, the parameter is processed up to the third right bracket exclusive. Strings encountered in the bracketed parameter are treated as such, and follow the rules for strings. Brackets contained in a string are not counted as part of the nesting level.

If the first character is a percent sign (%), then the expression evaluator is called to process the following valid expression. The expression must resolve to a defined absolute value. This value (16-bit unsigned) is then converted to a number in the current radix, which is then used as the parameter.

Otherwise, the item is treated as a regular old parameter.

Note that a special character in macros is the up-arrow. It causes characters to be taken literally. For instance, to pass an up-arrow (^) as a parameter, use two in succession. To pass a semicolon as a parameter, use ^;, which is equivalent to <;>. Try using the following parameter:

```
<This is a ^> and this is an ^^>
```

and see what you get.

One condition that occurs very often is a macro call with a missing or null parameter. This can be discovered at expansion time by using the special operator NUL. NUL returns a true value (-1) if what comes after it is nothing but tabs, spaces, comment field, or an end of line. Anything else will return a false value to NUL.

Look at the following example.

```

                                1
                                2 XX      EQU      55H
                                3
                                4 MAC1      MACRO    ?XX,?YY
                                5              DEFB    ?YY      ;SECOND
                                6              IF      NUL ?XX
                                7              EXITM
                                8              ELSE
                                9              IRPC    XX,?XX
                               10              LOCAL   LABEL
                               11 LABEL      DW      LABEL
                               12              DEFB    ^^XX
                               13              DEFB    '&XX'&1FH
                               14              ENDM
                               15              ENDM
                               16
                               17              MAC1      CONTROL, 'DATA'
0100      44 41 54 41A      1              DEFB    'DATA'      ;SECOND
0104      0104      B      2 ??0001      DW      ??0001
0106      55      B      3              DEFB    XX
0107      03      B      4              DEFB    'C'&1FH
0108      0108      B      2 ??0002      DW      ??0002
010A      55      B      3              DEFB    XX
010B      0F      B      4              DEFB    'O'&1FH
010C      010C      B      2 ??0003      DW      ??0003
010E      55      B      3              DEFB    XX
010F      0E      B      4              DEFB    'N'&1FH
0110      0110      B      2 ??0004      DW      ??0004
0112      55      B      3              DEFB    XX
0113      14      B      4              DEFB    'T'&1FH
0114      0114      B      2 ??0005      DW      ??0005
0116      55      B      3              DEFB    XX
0117      12      B      4              DEFB    'R'&1FH
0118      0118      B      2 ??0006      DW      ??0006
011A      55      B      3              DEFB    XX
011B      0F      B      4              DEFB    'O'&1FH
011C      011C      B      2 ??0007      DW      ??0007
011E      55      B      3              DEFB    XX
011F      0C      B      4              DEFB    "L'&1FH
                               18 ;
                               19              MAC1      ,XX
0120      55      A      1              DEFB    XX      ;SECOND
                               20
                               21              END

```

5. Listing Controls

TITLE <ANYTHING>

Listing Title. This defines a new title to be put at the top of subsequent pages of listing. Takes effect BEFORE this line is printed, so this can be used in the first line of your source file to put a title on the first page. The title may be up to 80 characters, and may be truncated by **Z80ASM** to fit on the page.

Note that any tabs are compressed to single spaces. CONFIG can enable or disable the listing of the source line containing the TITLE directive.

<ANYTHING> can be in one of two forms. If the first non-blank character is a left paren, then the token is assumed to be in the following form:

(STRING)

where STRING is a valid delimited string, like 'Hi there y''all'. The delimiting quotes do not become part of the stored string.

If the first non-blank character is not a left paren, then the stored string begins with the first non-blank up to the first semicolon or CR. For example

```
TITLE        This is my  'Title'
and
TITLE        ( 'This is my  'Title'')
```

are equivalent.

SUBTTL <ANYTHING>
\$TITLE <ANYTHING>

Listing Subtitle. This defines the subtitle to be used on subsequent listing pages. The subtitle can be up to 60 characters long. See TITLE for a definition of <ANYTHING>.

The default subtitle is the filename of the file being assembled. The subtitle is reset upon entry and exit to/from any INCLUDE file to the name of the current source file.

PAGE [PLENGTH][,PWIDTH]
EJECT [PLENGTH][,PWIDTH]
\$EJECT [PLENGTH][,PWIDTH]
***EJECT** [PLENGTH][,PWIDTH]

Top of Page. If no parameters are given, this pseudo-op causes a new page to be started in the listing. Otherwise, one or two parameters are expected, the first being the new page length in lines, and the second being the new page width in columns. The standard default page length and width are set with CONFIG. Note that spaces are allowed between the * and EJECT.

```
PAGE      80, 132      ;page = 80 lines by 132 columns
```

LIST
.LIST

Listing On. This is the default mode. This has effect only if a listing is being generated. This affects overall listing.
NLIST

.XLIST

No List. This pseudo-op stops all listing generation. This can be countered only by a subsequent LIST pseudo-op.

MTLIST

Multi-line List. This pseudo-op enables listing of extra lines generated when the given source line generates more than 4 bytes of output. The default case is to just list the first 4 bytes with the source line. For instance, the line

```
DEFB      'I Like Peanut Butter'
```

generates 20 bytes of code. The default case will just list the first four bytes, while MTLIST will cause 5 lines to be printed.

NMTLIST

No Multi-line List. This pseudo-op suppresses the listing of extra lines of output caused by more than 4 bytes being generated from one source line. This is the standard default case.

CLIST
.LFCOND

Conditional List. This pseudo-op enables listing of lines contained in FALSE conditional assembly blocks. Standard default is to list only the lines that are in TRUE conditional blocks.
NCLIST

.SFCOND

No Conditional Listing. This pseudo-op causes the suppression of listing output during FALSE conditional block processing. This is the standard default case.

.TFCOND

Toggle Conditional List. This pseudo-op causes the listing of conditional blocks to be turned OFF if it was ON, and ON if it was OFF.

.LALL

List All. This pseudo-op controls macro expansion listing only. It causes **Z80ASM** to list every line of macro expansion (does not override NLIST or .XLIST).

.SALL

Suppress All. This pseudo-op controls macro expansion listing only. It causes the suppression of all macro expansion listing.

.XALL

Partial List. This pseudo-op controls macro expansion listing only. .XALL causes **Z80ASM** to list only the lines that generate code output.

6. Miscellaneous Pseudo-ops

The ones that don't fit in anywhere else.

END [STARTADR]

End directive. This signifies end of input file to the assembler. The optional argument is used, in HEX and relocatable mode, to signify a starting address for the program. Note: this directive is ignored if encountered during a macro definition or within a FALSE conditional block.

END START ;start at start...

NAME <ANYTHING>

Module name. Valid only in relocatable code, this assigns a name to the generated relocatable module. If no name is defined, Z80ASM uses the source file name as the module name. See TITLE for a description of <ANYTHING>. Maximum size 16 chars. Syntax:

```
NAME        MYFILE
NAME        ('MYFILE')
```

.REQUEST <LIBLIST>

Request Library Search. This pseudo-op causes **SLRNLK** to search the given filename.REL for any undefined externals. The modules are loaded as needed. The given filename.REL is assumed to reside on the default disk at link time. Note that the filename may be eight characters long in M-REL format, but only six characters if you included a drive specifier. SLR Format allows eight in either case (actually 16, but CP/M filenames are limited to eight). Requests may pass more than one filename, separated by commas. They will be searched in the order in which they are defined. For example:

```
REQUEST      C:MYLIB,FORLIB
```

.Z80

This pseudo-op has no effect.

.CREF

Cross-reference ON. This pseudo-op turns on the cross-reference builder for the subsequent source lines. This is the default condition. This pseudo-op is useful only when cross-reference generation has been selected by a command line option or through CONFIG.

.XCREF

Cross-reference OFF. This pseudo-op turns off the cross-reference builder for the subsequent lines of source up to the next .CREF. Useful only when cross-reference generation is in use, ignored otherwise.

.COMMENT <delim>

Comment text. This pseudo-op is used to turn text into a comment. The next non-blank character defines the <delim>iter. The rest of the source file up to line containing the next <delim> character is considered a comment field. This is useful for commenting out a chunk of code without putting a semicolon at the beginning of each line.

.PRINTX

Print text. This pseudo-op takes the rest of the source line and places it on the console. It is useful in displaying messages, values of parameters (by passing the parameter using a leading % to a macro containing .printx), etc.

.RADIX <EXP>

Set input and output radix. This pseudo-op is used to change the default input and output radix from base 10 to something else in the range of 2-16. The default radix is set to 10 before the <EXP> is processed. This is usually used to enter a group of data in a base such as 16 without requiring the trailing H. It also affects the base used in processing macro parameters preceded by a %.

APPENDIX A - ERROR MESSAGE SUMMARY

There are many error conditions that **Z80ASM** can detect. This section describes the error messages that can be generated.

Error messages are of the form:

```
FILENAME - ERROR MESSAGE Line # ?????  
<This Line Is The Source Line That Contains The Error Condition>
```

where FILENAME is the name of the current file or macro being processed, and ????? is the line number of that file or macro on which the error was discovered.

Note: errors discovered while processing the intermediate code give code address instead of line number for the error.

Bad Dummy Param

Dummy parameters must follow the syntax for valid labels.

Bad File Name

Something is syntactically incorrect with the given file name.

Bad Opcode

Something was found in the opcode field that is not in the opcode list, pseudo-op list, or macro table.

Byte Out of Range

This can occur in several places, with meaning depending on the instruction involved. For relative jumps and indexed addressing, the value generated must lie within the range of -128 to +127. For BIT, RES, and SET instructions, the bit number must be between 0 and 7. For RST instructions, the operand must be 0, 8, 10H, 18H, etc. Finally, for the IM instruction, the operand must be 0, 1, or 2. Something other than these was calculated.

Comma Expected

Guess what? You're right, a comma was expected. Possibly something extra ahead of your comma, or else your comma is missing. Or something.

Expression Error

This error message will only be generated if the expression evaluator gets very confused. Should not happen...

Extra Operand

Look at that line closely, **Z80ASM** found more items on it than belonged. Possibly you just forgot a semicolon before your comment, but it may be more critical than that.

File Not Found

Z80ASM tried to open the given file unsuccessfully.

ID, (, or Unary Op Expected

The expression evaluator was looking for an ID (valid number or label), left paren, or Unary Operator (such as HIGH or LOW). Something else was there.

Illegal in Absolute File

A pseudo-op was encountered that is valid only in relocatable assembly.

Illegal - 0 used

The expression could not be evaluated down to the type required by the pseudo-op on this line. A zero was used instead.

Intermediate Corrupt

An item was found while processing the intermediate code that should not be there. Try to determine what led up to that and report the bug.

Line Too Long

Source lines are limited to 127 characters in length.

Macro Redef

Macro Table is confused about a macro redefinition. Possibly you redefined the macro differently on different passes through MACLIB, IF1, IF2 or some other conditional situation. Macro redefinition is allowed, but obviously must be the same on each pass.

Missing .DEPHASE

Something was encountered that is illegal inside a PHASE block. Possibly you forgot a .DEPHASE pseudo-op.

Missing ENDIF

Oops! End of file encountered while in a conditional. Where was your ENDIF ?

Missing ENDM

Oops! End of file encountered while building a macro. Probably a missing ENDM or MEND.

Missing IF

An ELSE or ENDIF without IF.

Missing MACRO

Something was encountered that is not legal outside a macro, such as an ENDM, MEND, or LOCAL.

Missing .PHASE

A .DEPHASE pseudo-op was found without a preceding .PHASE pseudo-op. Check your phase blocking.

No Backing Up in COM File

Only in absolute mode, COM type files. The address given in the ORG statement is smaller than the last location generated. You cannot go backwards while generating a COM file.

Out Of Memory

No room left in memory. Symbol table, macro table, include tables, cross-reference table, etc, must all fit into memory. Ask about Z80ASM+.

Previously Defined

This LABEL has been defined already elsewhere in the file and is being redefined with something other than a DEFL. Change the name of one of your labels.

String Syntax

Strings can contain only printable characters. Either your string contains a control character (such as a TAB), or you forgot the trailing quotation mark.

Symbol Expected

Something was found that is illegal as an operation or label. Probably something was mis-typed on the line.

Syntax Error

This message appears when the assembler is too confused to know what went wrong.

Too Many Commons

An attempt was made to define more than 12 common blocks. That is the limit. Ask about Z80ASM+.

Unexpected EOF

The end of the source file was found at an inopportune time.

')) Expected

Somewhat self-explanatory.

'/' Expected

Somewhat self-explanatory. Common block name must be delimited by slashes, and contain only valid label-type characters.

), Bin-op, or End of Exp Expected

Well, the expression evaluator was looking for one of the above, a right paren, a binary operator (an operator that takes two arguments, such as * or /), or an end-of-expression delimiter. Something else was there.

APPENDIX B - ZILOG Z80 INSTRUCTION SET

The following definitions are used throughout this description of the ZILOG Z80 Instruction Set.

cc	C, NC, Z, NZ, P, M, PE, or PO (V & NV allowed in Z80ASM in place of PE and PO)
dd	C, NC, Z, or NZ
nn	Any 16-bit number or expression
(nn)	Represents the contents of address nn
n	Any 8-bit number or expression
r	Register A, B, C, D, E, H, or L
d	A one-byte expression in the range -128 to 127
b	Expression in the range 0 through 7
ss	Register pairs BC, DE, HL, SP
pp	Register pairs BC, DE, IX, SP
qq	Register pairs BC, DE, HL, AF
rr	Register pairs BC, DE, IY, SP
ir	(HL), (IX+d), or (IY+d)
m	r, (HL), (IX+d), or (IY+d)
s	r, n, (HL), (IX+d), or (IY+d)
ADC HL,ss	HL = HL + Carry + ss
ADC A,s	Acc = Acc + Carry + s
ADD A,n	Acc = Acc + n
ADD A,r	Acc = Acc + r
ADD A,(ir)	Acc = Acc + (ir)
ADD HL,ss	HL = HL + ss
ADD IX, pp	IX = IX + pp
ADD IY,rr	IY = IY + rr
AND s	Acc = Acc AND s
BIT b,m	Z = BIT b of m
CALL cc,nn	IF cc is true, call subroutine at nn
CALL nn	Call subroutine at nn
CCF	Complement Carry
CP s	Set Flags as result of Acc - s
CPD	CP (HL), DEC HL, DEC BC
CPDR	CP (HL), DEC HL, DEC BC, Rpt till BC=0 or Acc=(HL)
CPI	CP (HL), INC HL, DEC BC
CPIR	CP (HL), INC HL, DEC BC, Rpt till BC=0 or Acc=(HL)
CPL	Complement Acc - Acc = -(Acc + 1)
DAA	Decimal Adjust Acc
DEC m	m = m - 1
DEC IX	IX = IX - 1
DEC IY	IY = IY - 1
DEC ss	ss = ss - 1
DI	Disable interrupts
DJNZ e	B = B - 1, if B<>, Jump to e
EI	Enable interrupts
EX (SP),HL	Exchange HL with (SP) top of stack
EX (SP),IX	Exchange IX with (SP) top of stack

EX (SP),IY	Exchange IY with (SP) top of stack
EX AF,AF'	Exchange AF with AF'
EX DE,HL	Exchange DE with HL
EXX	Exchange HL, DE, & BC with HL', DE', & BC'
HALT	Halt CPU till interrupt or reset
IM 0	Select Interrupt Mode 0
IM 1	Select Interrupt Mode 1
IM 2	Select Interrupt Mode 2
IN A,(n)	Acc = input from port n
IN r,(C)	r = input from port (C)
INC m	m = m + 1
INC IX	IX = IX + 1
INC IY	IY = IY + 1
INC ss	ss = ss + 1
IND	(HL) = input from port (C), DEC HL, DEC B
INDR	(HL) = input from port (C), DEC HL, DEC B, rpt till B=0
INI	(HL) = input from port (C), INC HL, DEC B
INIR	(HL) = input from port (C), INC HL, DEC B, rpt till B=0
JP (HL)	PC = HL (Jump to location (HL))
JP (IX)	PC = IX
JP (IY)	PC = IY
JP cc,nn	If cc is true, PC = nn
JP nn	PC = nn
JR dd.nn	If dd is true, jump relative to nn
JR nn	Jump relative to nn
LD A,(BC)	Acc = contents of location (BC)
LD A,(DE)	Acc = (DE)
LD A,I	Acc = I (Interrupt Vector Reg)
LD A,(nn)	Acc = location nn
LD A,R	Acc = R (Refresh Reg)
LD (BC),A	location (BC) = Acc
LD (DE),A	location (DE) = Acc
LD (ir),n	Store n in location (ir)
LD (ir),r	Store r in location (ir)
LD ss,nn	ss = nn
LD ss,(nn)	ss = contents of nn
LD I,A	I = Acc
LD IX,nn	IX = nn
LD IX,(nn)	IX = contents of nn
LD IY,nn	IY = nn
LD IY,(nn)	IY = contents of nn
LD (nn),A	Store a in location (nn)
LD (nn),ss	Store ss in location (nn)
LD (nn),HL	Store HL in location (nn)
LD (nn),IX	Store IX in location (nn)
LD (nn),IY	Store IY in location (nn)
LD R,A	Store A in R
LD r,(ir)	r = location (ir)
LD r,n	r = n
LD r,r	r = r
LD SP,HL	SP = HL
LD SP,IX	SP = IX
LD SP,IY	SP = IY
LDD	Location (DE) = Location (HL), DEC HL, DE, & BC
DDRR	(DE) = (HL), DEC HL, DE, & BC, REPEAT TILL BC=0

LDI	Location (DE) = Location (HL), INC HL & DE, DEC BC
LDIR	(DE) = (HL), INC HL & DE, DEC BC, Repeat till BC=0
NEG	Acc = -Acc
NOP	Nothing
OR s	Acc = Acc OR s
OTDR	Port (C) = (HL), DEC HL & B, Repeat till B = 0
OTIR	Port (C) = (HL), INC HL, DEC B, Repeat till B=0
OUT (C), r	Port (C) = r
OUT (n),A	Port n = A
OUTD	Port (C) = (HL), DEC HL & B
OUTI	Port (C) = (HL), INC HL, DEC B
POP IX	IX = (SP), SP = SP + 2
POP IY	IY = (SP), SP = SP + 2
POP qq	qq = (SP), SP = SP + 2
PUSH IX	SP = SP - 2, (SP) = IX
PUSH IY	SP = SP - 2, (SP) = IY
PUSH qq	SP = SP - 2, (SP) = qq
RES b,m	Reset bit b of m
RET	PC = (SP), SP = SP + 2 (Return from sub.)
RET cc	If cc is true, PC = (SP), SP = SP + 2
RETI	Return from interrupt
RETN	Return from non-maskable interrupt
RL m	Rotate m left through carry
RLA	Rotate Acc left through carry
RLC m	Rotate ma left circular
RLCA	Rotate Acc left circular
RLD	Rotate (HL) & Lower nibble of Acc left 4 bits
RR m	Rotate m right through carry
RRA	Rotate Acc right through carry
RRC m	Rotate m right circular
RRCA	Rotate Acc right circular
RRD	Rotate (HL) & Lower nibble of Acc right 4 bits
RST p	SP = SP - 2, (SP) = PC, PC = p (Single byte call)
SBC A,s	Acc = Acc - Carry - s
SBC HL,ss	HL = HL - Carry - ss
SCF	Set Carry Flag
SET b,m	Set bit b of m
SLA m	Shift m left arithmetic
SRA m	Shift m right arithmetic
SRL m	Shift m right logical
SUB s	Acc = Acc - s
XOR s	Acc = Acc XOR s

APPENDIX C - INTEL HEX FILE FORMAT

The HEX file optionally generated by **Z80ASM** is the standard INTEL format HEX file. The file consists of one or more records of ASCII text defined below.

Record Syntax

:NNAAAATTDDDDDDDDDDDDDDDDDDDDXX

The first character is a colon (:)

The next two characters (NN) define the record length (00 - FF)

If the length is non-zero:

AAAA Defines the load address of the record. It is forward reading, i.e., High byte first.

The next two characters are the record type. TT is always zero for data records, 01 for ending record.

The following NN*2 characters define the actual binary to be loaded starting at AAAA.

XX is a checksum byte which, when added to the sum of all the previous bytes in this record, gives a total of zero (mod 256).

If NN = 0, then the value at AAAA is the optional starting or execution address. A record length zero also signifies end-of-file.

APPENDIX D - CONFIG UTILITY

The configuration utility CONFIG.COM provided with Z80ASM allows easy customization of Z80ASM to a particular set of requirements. This section briefly describes its use.

To run CONFIG, type

```
A>CONFIG Z80ASM.COM
```

where Z80ASM.COM is the file name you want to customize.

CONFIG will respond with a series of questions requesting flag settings or item values. In parentheses is the current value of that item. You can modify the current value by typing a new one, or the item can be left the same by just entering a CR. The process can be aborted by typing a ^C. After the last question is answered, CONFIG will write out the new settings.

Now we will explain each question that CONFIG asks.

Page Width (80) -

The current default page width is 80 columns. Any listing output wider than that will be truncated. This should be set to the width of the printer you use most often, in columns (255 max). This parameter can be changed at assembly time with the PAGE pseudo-op.

Page Length (60) -

The current default page length is 60 lines. A form feed will be generated after every 60 lines of listing. This should be modified if your page size is different. This parameter can be modified at assembly time with the PAGE pseudo-op.

Special Bits

This allows you to modify the default assembly type, which is: absolute, COM-type, Lower to upper is enabled, no symbol table, no cross-reference, no automatic Externals. CONFIG tells you what the different bits in the byte stand for. You can toggle any bit by just typing in a number from 0 to 7. To leave that item the way it is, just type CR.

List more than 4 bytes of object code (N) -

The default setting is to list up to 4 bytes of object code for each source line. Any more than that (such as in a DB string) are not printed. A Y in this flag would cause extra bytes to be printed on successive listing lines, four per line. This flag has the same effect as the MTLIST & NMTLIST pseudo-ops.

List lines encountered during false conditionals (N) -

The default setting is to suppress the listing of lines encountered during a false conditional block. A Y in this flag will cause false conditional lines to be printed. This flag can be modified at assembly time by the CLIST and NCLIST pseudo-ops.

Form Feed at start of listing (N) -

The default setting causes no top-of-form to be issued before the first line is printed. This assumes that your printer is already at the top of a new page when the listing begins. If you want a leading Form Feed, just type a Y here.

Macro Listing Option - 1=.IALL, 2=.XALL, 4=.SALL (2) -

This controls the macro listing default setting. Read the descriptions of .LALL, .XALL, and .SALL to see if you want to change the default setting. You can change it by typing a 1, 2, or 4.

Generate 6 Significant in M-Rel instead of 7 (N) -

The Microsoft REL format supports 7 significant characters for globals and externals. However, most software that utilizes M-Rel format truncates to 6 characters (Fortran compatibility?). You have your choice of 6 or 7 characters of significance.

Print 16-bit values in logical direction (Y) -

This controls the byte order (in the listing) for 16-bit values when printed. If you prefer to see the bytes in the order generated, use an N. The default case prints the high byte first.

Suppress Lines Containing PAGE, TITLE, etc (N) -

This controls the listing of lines that contain the pseudo-ops PAGE, TITLE, and .PRINTX. A Y here will cause those lines to be suppressed from any listing.

Disable Interrupts (N) -

Z80ASM was written to take full advantage of the Z80 architecture and instruction set for reasons that are self-explanatory when you see it run. Certain systems that are 'Z80' CP/M machines do not provide a true Z80 environment. If your system is interrupt driven and destroys any Z80 registers on interrupts, a Y here will cause **Z80ASM** to disable interrupts whenever any special Z80 registers are in use. Interrupts will always be enabled during any system calls.

Force Form Feed before Summary (N) -

This allows you to control the summary printing. By default, the summary will be printed at the end of the listing. You can force the summary to be placed at the top of a new page by putting a Y here.

Form Feed at End of Listing (Y) -

This causes Z80ASM to issue a form feed at the end of all listing output. This usually makes it easier for you to remove the listing from your printer, and also sets the top-of-form for the next listing without wasting any paper. The Form Feed can be eliminated by typing an N here.

Time and Date in Listing (N) -

If you are running on a system that provides time & date, **Z80ASM** provides the ability to have the time and date printed on the title line of your listing. To enable this, put a Y here.

Special TIME & DATE Items

The next three questions may be ignored if you 1) answered H to the above question, or 2) you are running under an operating system that provides MP/M compatible time and date (CP/M Plus, TurboDos, etc.).

If your system supports time and date, but not the system call 105 to return time and date, you can still have **Z80ASM** utilize your time and date information. The information must either be in the same form as that supplied by CP/M Plus:

DW	DATE	;Number of days since 1 Jan 1978
		;with 0001 being 1 Jan 1978
DB	HOURS	;Hour of the day in BCD
DB	MINUTES	;Minutes of the hour in BCD

or it must be in ASCII, 16 chars max, terminated by a -1.

If you can get your time and date formatted like that somewhere in your system, you can just tell CONFIG that you are supplying the address of the data. If you need to have some code executed to retrieve the time and date, **Z80ASM** will optionally call a subroutine for you, you just supply the address of the routine. The routine must emulate the System Call 105, that being, **Z80ASM** will supply an address in DE where you should store one of the above structures. All Z80 registers are available for your use, just be careful not to get too deep on the stack (you have 30 bytes to play with). Then lastly you need to tell **Z80ASM** which structure type you are returning.

Take advantage of multi-sector I/O (Y) -

System call 12 tells **Z80ASM** whether multi-sector I/O is available or not, at least usually. Certain 'CP/M compatible' operating systems return a code saying they are CP/M Plus or MP/M compatible, but they don't support multi-sector I/O. If that is your case, you will need to answer N here.

Use Statement #'s instead of Line # in file (N) -

This allows you to choose between two different line-numbering schemes. Statement #'s are numbers assigned as the listing is generated. This causes numbers to be generated in numerical order even when macro's are expanded, include files processed, etc. Line #'s are the actual line number in the source file being processed. These reset to 1 on include files. macro expansions, etc, are fully nestable, and refer to the line # in the item being processed. These are the numbers used in error messages. Statement numbers can be more meaningful for cross-references using include files and macros.

Print Line/Stmt # first on listing line (N) -

This allows you to select the order of certain items in the listing line. A Y causes the line number to be listed first, whereas an N causes the hexadecimal values to be listed first. Suit yourself!

Number of errors on which to abort (100) -

This option provides a limit on the number of errors **Z80ASM** will process before aborting the current assembly. A value of 0 will cause this option to be ignored.

Number of lines per console page (0=no paging) (24) -

This provides paging for all console output, pausing for operator intervention after N lines. A value of zero causes this option to be ignored.

Number of bytes (1-60) per line of HEX output (32) -

This option allows you to specify the number of bytes per line when generating a .HEX file. Certain emulators, PROM programmers, etc are very particular about the format for 'Intel-Standard' HEX format.

Close & ReOpen file in 2-pass mode (N) -

This option is used for CP/M 'lookalikes' that don't like the way **Z80ASM** optimizes disk I/O. Molecular Computer users may need to set this flag when assembling files larger than one extent.

Require : if label not in column one (Y) -

This option allows full free form source lines. Be careful if you select N, because mistyped opcodes will be treated as labels, and no error generated.

Conditionals test only bit 0 (DRI compatibility) (N) -

This option, when set to N, causes 0 to be treated as false, and anything else as true. If this option is set to Y, then if bit 0 is off, that is false, bit 0 on is true, and all other bits are ignored.

Suppress IF parameter errors in 1 pass mode (N) -

This option will disable the reporting of IF operand errors in one-pass mode. IF operands containing forward references can cause different sections of code to be assembled on different passes, which will go undetected in one pass mode.

Ignore leading space & tab chars in IF <> types (Y) -

This option controls the significance of spaces and tabs in IF string parameter processing. IFB < > will return FALSE if this option is set to N (M80 compatible, space is not blank), but will return TRUE if set to Y.

Fill unused space with 0 (N) or FF (Y) in COM (N) -

This option is used to define the fill byte used in filling uninitialized space when generating a COM file.

Generate Empty External Chains (M-REL) (N) -

Normally symbols that are declared external but never referenced are not entered into the REL file. This option forces generation of all externals. Some compilers expect the assembler to strip unneeded externals, while others select library options by simply declaring labels external.

ASEG Default to 0H instead of 100H (N) -

The first ASEG encountered defaults to 100H for standard CP/M program generation. This can be changed to 0 for M80 compatibility.

ORG <ABSOLUTE> Yields Offset in Current Space (N) -

Normally an implied ASEG is performed when ORG is passed an absolute parameter. This option allows that absolute number to be treated as an offset in the current address space.

The next series of prompts allow you to change the extensions looked for or generated on several different files. To change the extension, just type a new one, otherwise type a CR.

Extension for source File (Z80) -

This is the source file being assembled. The default case looks for an extension of Z80. You can change it to ASM, MAC, SRC, or whatever you like.

Extension for relocatable File (REL) -

This is the extension generated when you are creating a binary output file in relocatable mode.

Extension for absolute binary File (COM) -

This is the extension generated when you are creating a binary output file in absolute core-image mode.

Extension for Intel-Hex format file (HEX) -

This is the extension generated when you are creating a binary output file in absolute Intel-hex (/H) mode.

Extension for listing file (LST) -

This is the extension used when generating a listing file to disk.

Extension for temporary file (\$\$1) -

This is the extension used for the temporary file generated if the intermediate code overflows in one-pass mode.

Extension for /I file (SUB) -

This is the extension looked for on the specified indirect command file.

Default Ext for MACLIB file (MAC) -

This is the default extension used for filenames given in a MACLIB or INCLUDE statement.

Leader String to send to printer (1B,51,) -

This allows you to specify a setup string of up to 8 bytes to be sent to the printer before a listing is started. You can use it to select compressed print, one-pass print, or just blank it out with an FF. Note that this string is sent only if you use the /P option, not a drive type of 'Y'.

Trailer String to send to printer (1B,4E,) -

This allows you to undo whatever you did above. Again, this is only done with a /P.

At this point, CONFIG writes the changes the specified file. That's it!

APPENDIX E - ASCII TABLE

ASCII CHARACTER SET

The ASCII character set consists of single codes in the range of 0 to 7FH inclusive. This is always nice to have around when you need it.

BIT 6		0	0	0	0	1	1	1	1
I 5	C	0	0	1	1	0	0	1	1
T 4	O	0	1	0	1	0	1	0	1
3210	ROW L	0	1	2	3	4	5	6	7
0000	0	NUL	DLE	SP	0	@	P	`	p
0001	1	SOH	DC1	!	1	A	Q	a	q
0010	2	STX	DC2	"	2	B	R	b	r
0011	3	ETX	DC3	#	3	C	S	c	s
0100	4	EOT	DC4	\$	4	D	T	d	t
0101	5	ENQ	NAK	%	5	E	U	e	u
0110	6	ACK	SYN	&	6	F	V	f	v
0111	7	BEL	ETB	'	7	G	W	g	w
1000	8	BS	CAN	(8	H	X	h	x
1001	9	HT	EM)	9	I	Y	i	y
1010	10	VF	SUB	*	:	J	Z	j	z
1011	11	VT	ESC	+	;	K	[k	{
1100	12	FF	FS	,	<	L	\	l	
1101	13	CR	GS	-	=	M]	m	}
1110	14	SO	RS	.	>	N	^	n	~
1111	15	SI	US	/	?	O	_	o	DEL

APPENDIX F - **LIMITED WARRANTY**

SLR Systems disclaims any warranty as to this product.

SELLER MAKES NO WARRANTY EXPRESS OR IMPLIED, AND ANY IMPLIED WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE WHICH EXCEEDS THE FOREGOING WARRANTY IS HEREBY DISCLAIMED BY SELLER AND EXCLUDED FROM ANY AGREEMENT.

Buyer exclusively waives its rights to any consequential damages, loss or expense arising in connection with the use of or the inability to use its goods for any purpose whatsoever.

No warranty shall be applicable to any damages arising out of any act of the Buyer, his employees, agents, patrons or other persons.

The remedies set forth herein are exclusive and the liability of Seller to any contract or sale or anything done in connection therewith, whether in contract, in tort, under any warranty, or otherwise, shall not, except as expressly provided herein, exceed the price of the equipment or part on which said liability is based.

No employee or representative of Seller is authorized to change this warranty in any way or grant any other guarantee or warranty.